



The **data-link layer** is responsible for transferring packets across a link which is the communication channel connecting two adjacent hosts or routers.

Examples of link-layer protocols include PPP and local area networks (LAN) such as Ethernet, and 802.11.

<ul> <li>Our goals:</li> <li>Understand principles behind data link layer services: <ul> <li>sharing a broadcast channel: multiple access</li> <li>link layer addressing</li> <li>LAN interconnection</li> </ul> </li> <li>Instantiation and implementation of various link layer technologies</li> </ul>	<ul> <li>Overview:</li> <li>Link layer services</li> <li>Point-to-point protocol     <ul> <li>PPP</li> </ul> </li> <li>Later on:     <ul> <li>LANs:         <ul> <li>Ethernet</li> <li>802.11</li> </ul> </li> <li>link layer addressing, ARP</li> <li>LAN interconnection         <ul> <li>hubs, bridges, switches</li> </ul> </li> </ul></li></ul>	
		2



Communication networks provide a communication service between two hosts. This communication path starts at the source host, passes through a series of routers, and ends at the destination host. At that layer, where we are not particularly concerned whether a device is a router or a host, hosts and the routers are referred to simply as **nodes**, and to the communication channels that connect adjacent nodes along the communication path as **links**. In order to move a datagram from source host to destination host, the datagram must be moved over each of the *individual links* in the path. The **data-link layer** is responsible for transferring a datagram that comes from the network layer across an individual link.



A link is the physical communication channels that connect either two host, two routers or a host-router pair. The **link-layer protocol** defines the format of the units of data (**frames**) exchanged between the nodes at the ends of the link, as well as the actions taken by these nodes when sending and receiving these data units. Each link-layer frame typically encapsulates one network-layer datagram.

A link-layer protocol has the node-to-node job of moving a network-layer datagram over a *single link* in the path. An important characteristic of the link layer is that a datagram may be handled by different link-layer protocols, offering different services, on the different links in the path.

### Link Layer Services

- Framing, link access:
  - encapsulate datagram into frame, adding header, trailer
  - implement channel access if shared medium,
  - 'physical addresses' used in frame headers to identify source, dest
    - different from IP address!
- Reliable delivery between two physically connected devices:
  - we learned how to do this already (cf. Transport Layer)
  - seldom used on low bit error link (fiber, some twisted pair)
  - wireless links: high error rates
    - link-level reliability to avoid end-end retransmission

Possible services that can be offered by a link-layer protocol include:

•*Framing and link access.* Almost all link-layer protocols encapsulate each network-layer datagram within a network-layer datagram is inserted, and a number of header fields. A data-link protocol specifies the structure of the frame, as well as a channel access protocol that specifies the rules by which a frame is transmitted onto the link. For point-to-point links that have a single sender on one end of the link and a single receiver at the other end of the link, the link-access protocol is simple (or non-existent)--the sender can send a frame whenever the link is idle. The more interesting case is when multiple nodes share a single broadcast link--the so-called multiple access problem. Here, the channel access protocol serves to coordinate the frame transmissions of the many nodes link-layer frame before transmission onto the link. A frame consists of a data field, in which the. The frame headers also often include fields for a node's so-called **physical address**, which is completely *distinct* from the node's network layer (for example, IP) address.

•*Reliable delivery.* When a link-layer protocol provides reliable-delivery service, it guarantees to move each network-layer datagram across the link without error. This is achieved with acknowledgments and retransmissions. A link-layer reliable-delivery service is often used for links that are prone to high error rates, such as a wireless link, with the goal of correcting an error locally, on the link where the error occurs, rather than forcing an end-to-end retransmission of the data by a transport- or application-layer protocol. However, link-layer reliable delivery can be considered an unnecessary overhead for low bit-error links, including fiber, coax, and many twisted-pair copper links. For this reason, many of the most popular link-layer protocols do not provide a reliable-delivery service.

### Link Layer Services (more)


- Flow Control
  - pacing between sender and receivers
- Error Detection
  - errors caused by signal attenuation, noise.
  - receiver detects presence of errors:
    - signals sender for retransmission or drops frame
- Error Correction
  - receiver identifies and corrects bit error(s) without resorting to retransmission
- Half-duplex and full-duplex


•*Flow control.* A link-layer protocol can provide flow control in order to prevent the sending node on one side of a link from overwhelming the receiving node on the other side of the link.

•*Error detection.* Many link-layer protocols provide a mechanism to detect the presence of one or more errors. This is done by having the transmitting node set error-detection bits in the frame, and having the receiving node perform an error check. Error detection is a very common service among link-layer protocols. Error detection in the link layer is usually more sophisticated than the one at the transport layer and network layers and implemented in hardware.

•*Error correction.* Error correction is similar to error detection, except that a receiver cannot only detect whether errors have been introduced in the frame but can also determine exactly where in the frame the errors have occurred (and hence correct these errors).

•*Half-duplex and full-duplex.* With full-duplex transmission, the nodes at both ends of a link may transmit packets at the same time. With half-duplex transmission, a node cannot both transmit and receive at the same time.







<ul> <li>Examples of protocols</li> <li>CRC - Cyclic Redundancy Check</li> <li>X.25 - LAPB</li> </ul>										
	addres	s contr	ol	data		CRC				
	8 bits	8 bit	S	variable	16	5 bits				
▪ Et	hernet									
	dest	source	type	data		CRC				
	6 bytes	6 bytes	2 bytes	46 - 1500 byte	es	4 bytes	5			
							8			


### Error detection in TCP/IP

- Checksum TCP/IP
  - sum of 16 bit words with carry in 1's complement
  - carry is added
  - 1's complement
- Characteristics
  - detects all simple errors
  - if data uniformly distributed, residual error rate 1/65536










A **point-to-point link** consists of a single sender on one end of the link, and a single receiver at the other end of the link. Many link-layer protocols have been designed for point-to-point links; PPP and HDLC for example. The second type of link, a **broadcast link**, can have multiple sending and receiving nodes all connected to the same, single, shared broadcast channel, where each node on the channel receives a copy of any sent frame, e.g. Ethernet. In shared broadcast channel there is the problem of how to coordinate the access of multiple sending and receiving nodes to a --the so-called **multiple access problem.** Broadcast channels are often used in **local area networks (LANs)**, networks that are geographically concentrated in a single building (or on a corporate or university campus). A NBMA link allows multiple and simultaneous dedicated access to the communication medium, but does not provide broadcast.



- One sender, one receiver, one link: easier than a broadcast link:
  - no Media Access Control
  - no need for explicit MAC addressing
  - e.g., dialup link, ISDN line
- Popular point-to-point DLC protocols:
  - PPP (point-to-point protocol)
  - HDLC: High level data link control (Data link used to be considered "high layer" in protocol stack!)


The **point-to-point protocol (PPP)** [<u>RFC 1661; RFC 2153</u>] is a data-link layer protocol that operates over a **point-to-point link**--a link directly connecting two nodes, one on each end of the link. The point-to-point link over which PPP operates might be a serial dialup telephone line (for example, a 56K modem connection), a SONET/SDH link, an X.25 connection, or an ISDN circuit. As noted above, PPP has become the protocol of choice for connecting home users to their ISPs over a dialup connection.





- Data
  - multi-protocol: IP packets, IPX packets, others
- Header compression IP, TCP
- Authentication

## Associated protocols

- LCP (Link Control Protocol)
  - activate a link
  - negociate options
  - test
- IPCP (IP Control Protocol)
  - network layer address negotiation:
    - hosts/nodes across the link must learn/configure each other's network address
- PAP (PPP Authentification Protocol)
  - password exchange









IPCP (IP Configuration Protocol)

NCP for IP: configure the network layer

address negotiation







Before any data is exchanged over a PPP link, the two peers (one at each end of the PPP link) must first specify the desired link configuration options using an LCP configure-request frame. Once the link has been established, link options negotiated, and the authentication (if any) performed, the two sides of the PPP link then exchange network-layer-specific network control packets with each other. In the case of IP protocol, IP control protocol (IPCP) is used.

### Data framing

- Frame format inherited from first packet switching networks
  - synchronous transmission with error recovery (HDLC)
  - Transpac (X.25 LAPB)
- PPP
  - start and end of frame delimitation
  - transparent data transmission
    - how to transmit characters used for delimitation?
    - byte stuffing
  - error detection polynomial code


PPP	PPP - frame formats									
flag	address	control	protocol	data	CRC	flag				
8 bits	8 bits	8 bits	8 or 16 bits	variable	16 bits	8 bits				
<ul> <li>Flag: 01111110 - 0x7e</li> <li>Address: 11111111</li> <li>Control: 00000011</li> <li>Protocol: LCP, IPCP, IP</li> <li>Data: 1500 bytes by default</li> <li>CRC: 16 bit CCITT polynomial code</li> </ul>										
						19				





#### Example PPP connection (logs)

- PPPoE connecting to service
- PPPoE connection established.
- Connect: ppp0 <--> socket[34:16]
- rcvd [LCP ConfReq id=0x81 <mru 1500> <auth chap MD5> <magic 0x4b4dcf02>]
- sent [LCP ConfAck id=0x81 <mru 1500> <auth chap MD5> <magic 0x4b4dcf02>]
- sent [LCP ConfReq id=0x2 <mru 1492> <magic 0x1f3f807b>]





#### **Example PPP connection**

- sent [LCP ConfAck id=0x12 <auth pap> <magic 0x794cb2ad>]
- rcvd [LCP ConfNak id=0x3 <mru 1500>]
- sent [LCP ConfReq id=0x4 <asyncmap 0x0> <magic 0x5893ae1e> <pcomp> <accomp>]
- rcvd [LCP ConfAck id=0x4 <asyncmap 0x0> <magic 0x5893ae1e> <pcomp> <accomp>]
- sent [LCP EchoReq id=0x0 magic=0x5893ae1e]
- sent [PAP AuthReq id=0x1 user="monlogin@isp" password=<hidden>]
- rcvd [LCP EchoRep id=0x0 magic=0x794cb2ad]
- rcvd [PAP AuthAck id=0x1 ""]
- sent [IPCP ConfReq id=0x1 <addr 0.0.0.0> <compress VJ Of 01>]
- rcvd [IPCP ConfReq id=0x48 <addr 192.168.254.254>]
- ipcp: returning Configure-ACK

#### **Example PPP connection**

sent [IPCP ConfAck id=0x48 <addr 192.168.254.254>]
rcvd [IPCP ConfRej id=0x1 <compress VJ Of O1>]
sent [IPCP ConfReq id=0x2 <addr 0.0.0.0>]
rcvd [IPCP ConfReq id=0x2 <addr 82.65.101.110>]
sent [IPCP ConfReq id=0x3 <addr 82.65.101.110>]
rcvd [IPCP ConfAck id=0x3 <addr 82.65.101.110>]
ipcp: up
local IP address 82.65.101.110
remote IP address 192.168.254.254





# Not provided by PPP

- error correction/recovery
- flow control
- sequencing

